



P&ID Reviews

Digitally redline P&IDs with customizable markup tools to improve communication and collaboration.

Markup Valves

Indicate valves on a P&ID using rectangles, circles, clouds, polygons or any other symbol, and give it a fill to show whether it should be open or closed.


Simply choose a shape from the **Markups list**, place it on the diagram and set your color preferences from the **Properties** panel.




In this example, the red rectangles represent closed valves and green rectangles represent open valves.

Highlight Isolation Lines

Use the **Highlighter**  to indicate isolated pipelines.

You can also use the **Line**  tool to make straight lines with ease.

Hold down the **Shift Key** while using the Highlighter and Line tool to create a straight line.





Number Valves Using Sequence Annotations

Revu includes annotations that automatically number valves sequentially as you place them on a P&ID. They can be found in the **Sequences & Actions** tool set in the **Tool Chest™**.

Simply select one of the sequencing annotations and begin placing them on your P&ID.

To stop the sequence, press **Esc**. To start a new sequence, select the annotation again from the Tool Chest.

To resume an existing sequence, just right-click on any annotation already included on the P&ID and choose **Resume Sequence**.




Custom Sequencing Valve Symbols


You can also create your own custom sequence annotations with your preferred shape, colors and sequencing format (i.e., numbers, letters, roman numerals etc.).




Choose a shape and place it on the P&ID.




Put a **Text Box** inside the shape and type in a number.




Select the entire markup, right-click on it and select **Group**.



Open the **Tool Chest** and move the newly grouped annotation from **Recent Tools** to **Sequences & Actions**.




Right-click the annotation, hover over **Sequence** and choose **Define**. Then set your preferences.



Digital Stamps

Revu provides a number of default stamp annotations that are fully editable and customizable.

Simply select the **Markup** button and open the **Stamp** dropdown to view the available stamps.



APPROVED

Watermark

Preliminary

09/26/2012 4:05:45 PM

Revised

09/26/2012 4:06:15 PM

PROPRIETARY DO NOT DISTRIBUTE

Draft Print

09/26/2012 4:05:26 PM

For Review


09/26/2012 4:05:35 PM



Custom Stamps

Select **Create Stamp** to customize your own unique stamp. Your custom stamp will be saved alongside the default stamps, available for easy reuse and re-editing.

Set your custom stamp preferences.



Customize the features and save.

